Music Studio

Version 1.6.1

User Manual

Music Studio is available on the App Store for all iPhone, iPod Touch and iPad models

Table of Contents

Quick Start Guide	1
Playing on the keyboard	1
Recording a song	2
Best practices	3
FAQ (Frequently Asked Questions)	4
Keyboard Tab	6
Introduction	6
Scrolling and resizing	6
Keyboard menu	6
Play button	6
Pause button (iPad only)	6
Loop button	6
Record button	7
Undo button	7
Display	7
Metronome button	7
Tempo Button (iPad only)	7
Keyboard layout button	7
Rows button (iPad only)	3
Key label button (iPad only)	3
Accelerometer button	3
Velocity (volume)	3
Keyboard layout mode	9
Octave buttons	9
Fullscreen button (iPhone only)	9
Keyboard map	9
Rows button (iPhone only)	9
Key label button (iPhone only)	9
Keyboard playhead mode	10
Rewind button	10
Bar reel buttons	10

Navigation map	10
Marker buttons	10
Instruments Tab	11
Introduction	11
Volume fader	11
Attack time fader	11
Release time fader	11
Category buttons (iPhone only)	11
Defaults button	11
Preview button	12
Keep attack/release times (iPad only)	12
Sync keyboard rows (iPad only)	12
Row indicator	12
Tracks Tab	13
Introduction	13
Scrolling	13
What is a track?	13
Track management	13
What is an event?	13
Common controls	14
Play button	14
Loop button	14
Pause button	14
Undo button	14
Display	14
Tempo Button	14
Zoom button	14
Horizontal zoom buttons (iPad only)	15
Track view switch	15
Tempo indicator	15
Song ruler	15
Song markers	15
Track zoom mode	16
Horizontal zoom buttons (iPhone only)	16
Vertical zoom buttons	16
Navigation map	16
Track playhead mode	17
Rewind button	17
Bar reel buttons	17
Navigation map	17

Marker buttons	17
Mixer	18
Track list	18
Rearranging tracks and changing the color	18
Gain bars	18
Warning triangle	18
Keyboard row icon	19
Filter track	19
Add track button	19
Mute button	19
Solo button	19
FX button	19
Edit button	19
Duplicate button	19
Delete button	19
Pan knob and volume slider	20
Sequencer	21
Track list	21
New selection button	21
Change selection button	21
Clipboard (copy and paste)	21
Move button	21
Duplicate button	22
Repeat button	22
Transpose button	22
Quantize button	22
Edit button	22
Delete button	22
Song bar edit button	22
Piano roll editor	24
Piano roll view	24
Vertical scrolling	24
New selection button	24
Change selection button	24
Draw button	24
Draw mode	25
Draw mode note buttons	25
Draw mode dotted button	25
Quantized drawing button	25
Move button	26
Duplicate button	26
Length button	26

	00
Volume button	26
Quantize button	26
Delete button	26
Quantization popup	27
Note buttons	27
Dotted button	27
Triplet button	27
Note length checkbox	27
Soft (humanize) checkbox	27
Tempo popup	28
Tempo	28
Signature	28
Effects Tab	29
Bus structure	29
Common Controls	30
Power button	30
Limit to FX tracks checkbox	30
Preview button	30
Default button	30
Volume	31
Master gain	31
Device volume	31
Decibel meters	31
Reverb	32
Reverb size	32
Reverb brightness	32
Reverb stereo spread	32
Reverb mix (wet/dry)	32
Reverb style	32
Reverb quality	32
Remember settings for each style (iPad only)	32
Delay	33
Timing buttons	33
Timing switch	33
Feedback	33
Delay mix (wet/dry)	33
Equalizer	34
Amplifier	35
Overdrive	35
Style	35
Filter	36

Resonance/Frequency display	36
Filter type switch	36
Filter accelerometer axis	36
Accelerometer sensitivity	37
Snap back checkbox	37
Pitch	38
Semitone slider	38
Sensitivity slider	38
Pitch bend accelerometer axis	38
Pitch bend invert axis checkbox	38
Pitch bend record mode	38
Projects Tab	39
Introduction	39
Filename textfield	39
File list	40
Beats	40
iTunes File Sharing	40
File Associations	41
Buttons	41
New	41
Load	41
Save	41
Delete	41
Export	42
Server	42
Setup Tab	43
Differences on the iPad	43
General settings	43
Latency	43
Polyphony	43
Continuous playhead movement	44
Lock interface orientation (iPhone only)	44
Hardware section	44
Restore defaults button	44
Keyboard settings	45
Velocity control	45
Snap to white keys	45
Allow touches between black keys	45
Allow touches on key borders	45
German key labeling	45

Auto quantization	45
Transposition	45
Accelerometer settings	46
Threshold slider	46
Reactivity slider	46
Calibration	46
Interface settings	47
Instruments tab	47
Keep attack/release times on instrument change (iPhone only)	47
Tracks tab	47
Scroll on the margins when moving notes	47
Centered zooming	47
Effects tab	47
Remember reverb settings for each type (iPhone only)	47
Metronome settings	48
Volume	48
Style	48
Precount	48
Precount only at song start	48
External Hardware	49
Hardware Configuration Popup	49
MIDI IN	49
MIDI OUT	50
Port	50
MIDI Panic	50
Send Params	50
Line 6 MIDI Mobilizer	50
Akai SynthStation 25	50
Core MIDI	50
Troubleshooting Guide	51
Version history	52
Version 1.6.1	52
Version 1.6	52
Version 1.5.1	53
Version 1.5	53
Version 1.4	55
Version 1.3	56
Version 1.2.1	57
Version 1.2	57

Version 1.1	58
Version 1.0.3	59
Version 1.0.2	60
Version 1.0.1	61
Version 1.0	63

Quick Start Guide

Playing on the keyboard

You can adjust the size and position of the keyboard by making a slide or pinch gesture anywhere on the menu bar.



- To change the labels on the keys, press the keys button and switch between the 4 key label modes with the key label button.
- Select the instrument of your choice from the scrollable instrument list in the Instruments tab.
- Adjust the attack/release sliders in the instruments tab to change the fade in/out times.



- In the Keyboard tab, tap the accelerometer button to enable pitch bend, then tilt your device to bend the played note's pitch.
- Tapping the keys button brings up a menu for switching to 2 keyboard rows, changing the key labels, and a keyboard map that allows to to position the keyboard with a single tap.




- Load a beat in order to play on top of a rhythm: tap the *Projects* tab, double tap the <u>Beats</u> folder and double tap a beat to add it to your song.
- Effects can be added in the Effects tab. The sound is greatly influenced by the reverb. Adjust the reverb type and size in the effects tab to simulate a specific room. High quality reverb sounds better but may introduce playback stuttering on older devices.

Recording a song

Follow these steps to create a simple song from scratch:

- Open the projects tab and tap the New button to create a new project.
- Open the tracks tab and tap the tempo button to set the tempo and signature of your new song.
- Open the instruments tab and select your instrument of choice.





- If you made a mistake and want to re-record, simply tap the undo button to erase the notes you just recorded.
- Switch to the tracks tab to review what you just recorded. The track can be edited bar-wise (sequencer) and note-wise (piano roll editor), more on this topic in the tracks tab section.



- Tap the plus icon to create a new track.

 The keyboard and instruments tabs always apply to the active track, so make sure that track 2 is selected.
- Repeat the previous steps to record something on the second track.
- Let's assume that your song has a duration of 20 bars and you want to start recording at bar 10. In the tracks tab, move the left marker on the ruler to the 10th bar and recording will always start from there.
- Tune the reverb in the effects tab, maybe set the equalizer and play around with the other effects.
- To save your song, open the projects tab, enter a song name in the text field and tap the save button.

Best practices

Use higher latency for editing

Change the <u>latency</u> setting in the setup tab to achieve the best performance: low latency is best for recording and playing on the keyboard, while high latency minimizes stuttering when editing a complex song.

Avoid overlapping (red) notes

Congruent (identical) and overlapping notes are marked red in the tracks tab. Congruent notes result in higher note volume, if the effect is unwanted just delete the top note.

Make use of the undo button

If you misplaced a note while recording, don't even hit the stop button but instead tap the undo button, tap undo and restart recording.



Try different quantization parameters

Every recording requires its own set of <u>quantization</u> parameters. Better results are obtained if you don't just stick with quantizing everything with 1/16. Try different settings and hit the undo button in between.

Release times can simulate legato

If a recorded melody should flow but it sounds more like staccato, the notes are simply too short. The perfect correction would be to manually increase the note lengths in the <u>piano roll editor</u>, but there is a quicker way: increase the track's release time until it sounds like legato.

Adjust the reverb quality

Reverb requires a lot of CPU power. If stuttering occurs during playback, decrease the reverb quality. Set it to high quality before you export your final song to wav.

FAQ (Frequently Asked Questions)

For more support-related discussions, please refer to the Forum on the Music Studio website.

I want to install the app on my second device. Do I have to pay for it again?

No. If you still have the app on your Mac/PC, simply sync with iTunes to install it again.

In general, you can "buy" (download) an app multiple times with the same account, the iTunes Store won't debit your credit card twice. However, the App Store will not indicate that you already bought the app, it will display a *buy* button and ask for your permission, only then you will be informed that it will be a free download.

Do I lose my songs if I remove the app from my device?

Yes, if you tap and hold the app icon and tap X to remove the app, all files and settings are deleted too. Even if you sync the app back from iTunes onto your device, it will be a fresh install and your files won't be restored. In order to save your songs, transfer them to your Mac/PC with iTunes file sharing. If you restore your iDevice by pressing the restore button in iTunes, your songs will be restored automatically (along with a reinstallation of iOS and all other apps).

How do I restore my purchased instruments or get them on my second device?

Simply enter the shop, tap the restore button in the upper right corner, enter your iTunes username and password, and wait for the instruments (which you already purchased) to appear in the instrument list. This process can take up to a few minutes depending on your connection speed (preferably WiFi).

Why is the price \$0.99 for a single instrument?

This is the lowest possible price on the app store. The package's prices are much lower compared to buying the instruments individually.

How to maximize the sound quality of the instruments?

To get the most out of the high quality studio-recorded instruments, use earphones or external speakers. Most instruments are designed for a specific tonal range, an E-Bass sounds as unreal in the 4th octave as a flute in the lowest octave. Some instruments also benefit from a higher or lower release time.

- Wind instruments in general sound best with a low release time and the reverb set to hall or canyon.
- A great effect for synths is to set the delay to 1/8th and dotted.
- String instruments sound best with a medium attack time (around 0.5s) and maybe a high release time.
- Keyboard instruments and guitars get a sustain feeling with a high release time.

If I select and edit bars in the sequencer, why are some notes ignored?

Selected notes are colored dark blue. If you select a bar but a note starts a few ticks earlier than this bar, it will not be selected. If possible, quantize the track, thereby aligning the notes to simplify further editing.

Why are the drum kit's sounds arranged in such a strange way?

This "strange way" is called the "General MIDI Level 1 Percussion Key Map". It is commonly used on nearly every hardware keyboard/synthesizer to retain full MIDI compatibility.

Why is the default instrument volume 80% and not 100%?

This way you don't have to change all the other track's volumes if you want one track to be louder.

Why doesn't the preview button play a nice melody?

Because it would be distracting for a musician who has a melody in mind while composing music.

Why is the app size so large?

Studio-sampled instruments require a lot of space. We decided not to trade quality for app size.

Which features will be included in future updates?

Please refer to the Forum on the Music Studio website for more feature-related discussions.

Keyboard Tab

Introduction

Music Studio features a 85-key clavier capable of handling up to 5 simultaneous touches (10 on the iPad). Not every instrument has the full tonal range, hence the number of playable octaves varies from instrument to instrument.

If you are uneasy with the way the keys react to your input, the setup tab offers some handy keyboard preferences.

Scrolling and resizing

The keyboard position and width can be adjusted via the scroll and pinch gestures. Either tap the keyboard layout button or simply do the gesture on the top menu bar: move one finger left or right to slide the keyboard, pinch with two fingers to adjust the key width.



Keyboard menu



Play button

Starts and stops playback of the song. Stop rewinds to the left marker.



Pause button (iPad only)

Simply pauses playback, like stop but without rewinding.



Loop button

Toggles looping, i.e. during playback and recording the song (or the section between the markers) will be repeated indefinitely.



Record button

Start or stop a new recording. More on this topic in the tracks tab.



Undo button

Tap to undo the last recording, hold for 2 seconds to display a popup with the possible undo/redo actions.



Display



The LCD displays the current instrument and the position of the playhead in the format measure-dot-beat, e.g. 7.2 means that the playhead is in the 2nd beat of the 7th bar (measure). Tap it to enter the <u>playhead mode</u>. A small white dot in the upper left corner indicates that the current track is not empty.



Metronome button

Toggles the metronome. Its state is remembered separately for playback and recording. Per default, the metronome is enabled only at recording. Beat and signature can be configured in the tempo popup in the tracks tab. Metronome volume and style settings are found in the setup tab.

iPhone/iPod touch only: tap and hold the metronome button to bring up the tempo popup.



Tempo Button (iPad only)

Toggles the tempo popup.



Keyboard layout button

Toggles the keyboard layout mode.



Rows button (iPad only)

Switches between one and two keyboard rows. More on this topic here. On the iPhone, this button can be found in the keyboard layout mode.



Key label button (iPad only)

Switches between the 4 key label modes: off, C only, all keys labeled, and colored key labels. On the iPhone, this button can be found in the keyboard layout mode.



Accelerometer button

Toggles the accelerometer input. By default, it enables the <u>pitch bend effect</u>. Tilt your device to bend the pitch of the currently played notes. The <u>filter effect</u> can also be configured to react to the accelerometer.

If this button is enabled while recording, the device tilt is also recorded (which could affect the pitch bend and/or the filter effect). In this case, the filter track will be overwritten unless you disable the accelerometer button or the accelerometer checkbox of the <u>filter effect</u>.

Velocity (volume)

In the setup tab, enable <u>Velocity</u> to control the note volume. If set to Touch-Y, the volume depends on where you touch a key (upper end quiet, lower end forte). The Accel setting allows you to control the note volume with the accelerometer by tilting the device.

Keyboard layout mode

In this mode, the keyboard rows can be scrolled and resized anywhere on the screen.





Octave buttons

The left and right octave buttons quickly scroll the keyboard one octave (12 semitones) down or up.



Fullscreen button (iPhone only)

Switches to the full screen keyboard.

Keyboard map



The map illustrates which part of the keyboard is currently visible. Slide or tap it to quickly scroll the keyboard.



Rows button (iPhone only)

Switches between one and two keyboard rows. More on this topic here.



Key label button (iPhone only)

Switches between the 4 key label modes: off, ${\bf C}$ only, all keys labeled, and colored key labels.

Keyboard playhead mode

Tap the LCD in the menu bar to enter the playhead mode. It allows you to adjust the position of the playhead and to set the markers. Use the controls in the bottom menu or simply slide your finger anywhere on the screen to adjust the position of the playhead.





Rewind button

Rewinds the playhead to the left song marker. Tap it a second time to rewind to the beginning of the song.



Bar reel buttons

Rewind and forward the playhead position by exactly 1 bar (measure).

Navigation map



Tap or slide it to quickly position the playhead anywhere in the song. Areas outside the markers are darkened. The map also displays the current track's notes as white lines.



Marker buttons

Set the left or right song marker to the current playhead position. The markers must be at least 1 bar apart. Why markers? Recording always starts at the left marker. The loop button loops the section between the markers. When exporting to a wav file, you can choose to only export the range between the markers.

Instruments Tab

Introduction

Change the selected track's instrument by tapping an instrument from the scrollable list.



Volume fader

Sets the current track's gain, like the volume slider in the mixer does.

Attack time fader

Controls the fade-in time, i.e. how long it takes for the instrument to reach its volume. Use longer attack times for soft sounds like strings and synth pads.

Release time fader

Controls the fade-out time, i.e. how long the sound fades out after a key is released. Use longer release times for simulating legato or one-shot for drum kits and percussive instruments.

Category buttons (iPhone only)



The category buttons filter the instrument list to show all instruments or just one category.



Defaults button

Resets the three sliders to the instrument's default preset. If "Keep attack/release" is disabled in the setup tab, this button is automatically pressed each time you select an instrument.



Preview button

Plays one or more notes (alternating) with the current instrument.

Keep attack/release times (iPad only)

If this checkbox is disabled, each time you select an instrument its default attack and release time will be set. If enabled, the current track's attack/release durations are kept when you select another instrument. On the iPhone, this setting can be found in the <u>setup tab</u>.

Sync keyboard rows (iPad only)

Enable this checkbox to synchronize the settings (instrument, volume, attack and release time) of both keyboard rows. Every change you make will affect both rows and thus two tracks.



Row indicator

Tap the lower row to switch to 2 keyboard rows. This control then allows you to switch between them to select different instruments for the upper and lower keyboard row. More on this topic here.

Tracks Tab

Introduction



Scrolling

Analogous to the keyboard tab, sliding and pinching on the menu bar scrolls and zooms the visible range of the song.

What is a track?

Think of a track as one instrumentalist in a band or an orchestra. It holds recorded notes (events), one instrument and some parameters. There can be multiple tracks with the same instrument but different parameters (e.g. volume, pan, attack/release time).

Track management

Only one track can be selected at a time. The keyboard will play this track's instrument, the record button will record on this track, and all the changes you make in the instrument tab will apply to it. You cannot delete the first track, the maximum number of tracks is 128. If you switch to two keyboard rows, a separate track for the lower row is created (more on this topic here)

What is an event?

A recorded note places 2 events on a track: key-down and key-up (also called note-on and note-off). The position of an event is stored with a resolution of 48 ticks per beat, which equals to 192 ticks per bar with a signature of 4/4, meaning that the shortest note can be a 1/192th.

Common controls



Play button

Starts and stops playback of the song. Stop rewinds to the left marker.



Loop button

If looping is active and the playhead reaches the right song marker (by default the song end), it will jump to the left marker and continue playback from there. This allows you to loop any part of the song, the markers can be moved in the song ruler.



Pause button

Simply pauses playback, like stop but without rewinding.



Undo button

Tap to undo the previous action. Hold for 2 seconds to display a popup with the possible undo/redo actions. If the result would not be obvious, the popup appears anyway (e.g. if you would undo a recording but switched to the tracks tab, or if only redo is possible). Selection does not count as an action.



Display



The LCD displays the position of the playhead in the format measure-dot-beat, e.g. 7.2 means that the playhead is in the 2nd beat of the 7th bar (measure). Tap it to enter the <u>playhead mode</u>. The display also shows parameter values (pan, volume, transposition) while you are changing them, and the currently selected note range in the piano roll editor.



Tempo Button

Toggles the tempo popup.



Zoom button

Toggles the zoom mode.




Horizontal zoom buttons (iPad only)

Zoom the ruler in or out. Tap the zoom-out button a few times to view the whole song. On the iPhone, these two buttons can be found in the zoom mode.



Track view switch

Switches between the mixer and the sequencer.



Tempo indicator

Displays the song tempo, bpm stands for beats per minute. Double tap it to enter the tempo popup.

Song ruler



The numbers and the vertical lines indicate the measures (bars), the short vertical lines are beats. The ruler also holds the playhead (white vertical line) and the markers (triangles). Slide anywhere on the ruler to position the playhead.

Song markers



The left and right song makers are located on the ruler and can be moved to a certain song position. An alternative method for positioning the markers is via the <u>playhead mode</u>.

Why markers? Recording always starts at the left marker. The loop button loops the section between the markers. When exporting to a way file, you can choose to only export the range between the markers.

Track zoom mode

In this mode, the view (i.e. the ruler) can be scrolled and resized anywhere on the screen.





Horizontal zoom buttons (iPhone only)

Zoom the ruler in or out. Tap the zoom-out button a few times to view the whole song.



Vertical zoom buttons

Only visible in the piano roll editor for zooming the mini keyboard.

Navigation map



Tap or slide it to quickly position the viewed range. Areas outside the visible range are darkened. The map also displays the current track's notes as white lines.

Track playhead mode

Tap the LCD in the menu bar to enter the playhead mode. It allows you to adjust the position of the playhead and to set the markers. Use the controls in the bottom menu or simply slide your finger anywhere on the screen to adjust the position of the playhead.





Rewind button

Rewinds the playhead to the left song marker. Tap it a second time to rewind to the beginning of the song.



Bar reel buttons

Rewind and forward the playhead position by exactly 1 bar (measure).

Navigation map



Tap or slide it to quickly position the playhead anywhere in the song. Areas outside the markers are darkened. The map also displays the current track's notes as white lines.



Marker buttons


Set the left or right song marker to the current playhead position. The markers must be at least 1 bar apart. Why markers? Recording always starts at the left marker. The loop button loops the section between the markers. When exporting to a wav file, you can choose to only export the range between the markers.

Mixer

The mixer is designed to edit whole tracks and set their volume and pan.



Track list



The track list allows you to select a track and scroll the list of tracks. Each track row holds its number, instrument icon, mute/solo/FX icons (see below), the keyboard row icon (if 2 rows), and the recorded notes as lines. Move your finger across the note area to scroll the playhead and get an audio preview. Double tap any region of a track to enter the piano roll editor.

Congruent (identical) and overlapping notes are marked red. Delete congruent notes and move overlapping notes to an additional track.

Rearranging tracks and changing the color

Tap and hold a track's instrument icon for 1 second. A tip box will appear, instructing you to slide vertically to move the track or horizontally to change the track's color.

Gain bars

These 2 green bars show the track's output gain for the left and right stereo channel, allowing you to see the volume and pan for each track at one glance. If the pan is centered, both bars have the same height.

Warning triangle

Indicates that some notes on the track are outside the instrument's note range. Tap it to see more information. Notes outside the range will be played back but may sound atypical for this instrument, since every real instrument has a limited range of playable notes.

Keyboard row icon

Only visible if 2 keyboard rows are enabled, indicating which keyboard row the track is assigned to. If you switch to two keyboard rows, a separate track for the new row will be created. Selecting a track will always assign it to the upper row. However, the track assignment of the lower row cannot be changed. If you switch back to one row, the lower row's track will be deleted if nothing has been recorded on it.

Filter track

The filter track appears only if the <u>filter effect</u> is enabled. The 2 lines represent the cutoff frequency and the resonance, like in the filter's panel. With the filter track selected, only the mute and the delete buttons are enabled. Muting the filter track prohibits it from being played back, allowing you to experiment with new filter settings.



Add track button

The add track button is located at the end of the track list. It adds a new track with the current instrument to the bottom of the list.



Mute button

Mutes the selected track, excluding it from playback. Muted tracks are darkened and are indicated by the mute icon.



Solo button

If one or more tracks are switched to solo, all non-solo tracks will be excluded from playback.



FX button

Sets the effects bus of the selected track. In short, effects with FX enabled act only on tracks that have FX enabled. The other effects are applied on all tracks except the ones with the crossed out FX icon.

Per default, all standard effects apply to the track. Tap the FX button once to mark the track as an FX track, meaning that also the FX effects apply, in addition to the default effects. Tap the button again to exclude the track from all effects (useful for raw drum and base sounds). The blue FX icon next to the track icon indicates each track's FX state.



Edit button

Switches to the piano roll editor for the selected track.



Duplicate button

Duplicates the selected track, thereby copying its parameters and recorded notes.



Delete button

Brings up a popup with the options to deleted or clear a track. Clear will delete its notes but leave the track in the list. Delete will remove the track from the list. If the track holds pitch bend events, a checkbox for clearing only the pitch bend data appears.

Pan knob and volume slider



The pan knob controls the track's stereo pan. Touch it and move your finger left or right to change the selected track's stereo pan. Double tap it to reset the pan to 0 (center). The LCD displays the current value (left is -127, center is 0, right is +127).

The volume slider displays and sets the track's volume. Its function is identical to the instrument tab's volume slider. The LCD displays the current value from 0 to 100%.

Sequencer

The sequencer is designed for quick, bar-wise editing of the song. Select a range of bars (measures) and delete, repeat, move, or transpose them.



Track list

The sequencer's track list is almost identical to the mixer's track list. Since the sequencer edits bars, track selection is not possible and the current track is not highlighted. Tapping a track's instrument icon will select all bars on the track.



New selection button

Clears the current selection and starts a new one. Tap it, then draw a rectangle on the note area in order to select bars. Selected bars are highlighted white and their notes are colored dark blue. Tap a track's instrument icon to select the whole track.



Change selection button

Adds or subtracts bars from an existing selection. Tap the button, then tap an unselected bar to add it to the selection, or a selected bar to deselect it. Tap a track's instrument icon to (de)select the whole track.

Clipboard (copy and paste)

The clipboard holds a selection of bars which is retained even if another project is loaded. To copy something from one song into another, make a selection, then tap and hold until the copy button appears. Tap copy, load the other song and go back to the sequencer screen. Tap and hold where you want to paste the contents of the clipboard, then tap the paste button.



Move button

Activates the move mode where the selected bars can be dragged around. The song length can be increased by moving bars past the song end.



Duplicate button

Duplicates the selected bars and selects the new ones which can be moved around immediately. The copied notes will appear red until they are moved, because they are congruent (identical) with the originals.



Repeat button

Duplicates the selected bars and moves them to the right so that they start where the selection ended. The song length is automatically increased if the new bars reach past the song end.



Transpose button

Brings up the transpose menu which allows you to change the tone pitch of the selected bars. The semitone buttons de/increase it by one semitone, the octave buttons by 12 semitones. The <u>LCD</u> displays the number of semitones currently transposed.





Quantize button

Tap the quantize button to bring up the quantization popup for quantizing the selected bars.



Edit button

Switches to the <u>piano roll editor</u> for the selected track. This button is disabled if the selection encompasses more than one track.



Delete button

Deletes the notes in the selected bars.



Song bar edit button

Toggles the song bar edit mode where whole bars can be inserted and cut from the song. Tap anywhere to select a bar of the song (not just of individual tracks), which gets highlighted in red. The cut button deletes all notes in the selected bar and cuts it, i.e. shifts all later notes one bar to left and decreases the song length by 1 bar. The insert

button inserts an empty bar at the position of the vertical line left to the red area. This means that the song length is increased by 1 bar and all notes to the right of the line are shifted one bar to the right.



Piano roll editor



Piano roll view

In contrast to the mixer and the sequencer screen, the piano roll editor displays only one track. The horizontal song ruler is still the same, but the vertical axis now represents keys. The mini keyboard on the left serves as a ruler for the note pitch. The background has the track's color scheme, where the dark stripes represent black notes. White horizontal lines between B and C keys mark the octaves. Notes are displayed as blocks, the color indicates the volume (velocity) from dark blue (silent) to green (default) to yellow (loudest).

Congruent (identical) and overlapping notes are marked red. Congruent notes result in higher note volume. Delete congruent notes and move overlapping notes to an additional track.

Notes with pitch bend data have a different texture.

Vertical scrolling

Slide vertically on the mini keyboard to scroll and do the pinch gesture to zoom vertically. At low zoom factors, selecting individual notes is nearly impossible, but of course greater note ranges can be selected at once.



New selection button

Clears the current selection and starts a new one. Tap it, then draw a rectangle in order to select notes. Selected notes are highlighted and the note range of the whole selection is displayed in the <u>LCD</u>.



Change selection button

Adds or subtracts notes from an existing selection. Tap the button, then select a range to toggle it.



Draw button

Tap it to enable the draw mode.

Draw mode



In the draw mode, notes can be created without recording on the keyboard. A crosshair, an OK button and a new menu will appear. Underneath the crosshair, the translucent note is the one which will be created if you press the OK or the Done button. Move the crosshair to the desired note location and tap OK to create the note - immediately, a new translucent note awaits creation. The song length can be increased by dragging the crosshair past the song end. Press the done button to exit the draw mode.



Draw mode note buttons

The selected note button defines the length of the note to be drawn.



Draw mode dotted button

Increases the note length by 50%.



Quantized drawing button

Quantizes the new note even before it is drawn. If this button is enabled, the crosshair snaps to a raster defined by the selected note button.



Move button

Activates the move mode where the selected notes can be dragged around.

The buttons in the menu (notes, dotted, done) have the same function as in draw mode. The OFF button disables quantization and allows for (almost continuous) movement with 1/192th precision. Tap one of the lock buttons to lock horizontal or vertical movement, which is very handy if you intend to move or transpose only.





Duplicate button

Duplicates the selected notes and selects the new ones which can be moved around immediately. The copied notes will appear red until they are moved, because they are congruent (identical) with the originals.

Important: Not moving the new notes will cause them to be identical (colored red) to the originals. They will be played back with increased volume.



Length button

Tap it to enable the length edit mode which brings up a new menu. The buttons in this menu (notes, dotted, quantize, done) have the same function as in draw mode. Either tap a note button to set the length of all selected notes to an absolute value, or move your finger horizontally to de/increase the relative length.



Volume button

Toggles the volume mode where the volume (also called key velocity) of the selected notes can be modified by moving your finger vertically. The <u>LCD</u> displays the current volume of the first selected note, ranging from 0 to 127 (default is 100). The note color indicates the volume from dark blue (silent) to green (default) to yellow (loudest).



Quantize button

Brings up the quantization popup for quantizing the selected notes.



Delete button

Deletes the selected notes.

Quantization popup



Quantization is the most important step after recording because it corrects the timing. If the quantization raster (resolution) is one quarter note, every selected note is moved to the nearest raster point in a 1/4 note raster. The selection of the right raster is crucial, therefore you might want to try out different settings for each recording. For example, if you played a rather fast melody and quantized it to 1/4, the timing will be ruined - in this case, just tap the undo button and try again with a higher resolution like 1/16. On the other hand, quantizing notes with a high resolution might not correct all timing errors you made when recording them.



Note buttons

Set the quantization raster (or resolution) by selecting a note. In practice, low resolutions like 1/4 are the right choice for slow notes like the background cello in the demo "Canon in D (Pachelbel)". 1/16 fits to most melodies, while at 1/32 you will only notice the difference if you recorded fast notes (like a fast drum pattern) or at a low tempo setting.



Dotted button

Increases the quantization raster by 50%. For example if you selected 1/8 dotted, the quantization resolution is 1/6 of a bar.



Triplet button

Treats the notes as triplets, meaning that the raster interval is multiplied by 2/3. This allows for more swing and quantization of Jazz style melodies. Naturally, dotted and triplet cannot be enabled at the same time.



Note length checkbox

If checked, note lengths will also be quantized, meaning that every note length will be an integer multiple of the selected quantization. This is especially handy if you want to enforce legato.



Soft (humanize) checkbox

If you want to keep a human touch to the recording, soft quantization will shift every note by just 50%, keeping it slightly off the perfect timing.

Tempo popup



Tempo

Tap or hold the +/- buttons to change the tempo in the range of 40 to 240 bpm (beats per minute). A faster way to set the tempo is to tap and slide the value on the LCD. An alternative tempo input method is to tap the Tap Tempo button with the desired tempo for at least two times. Hold the Preview button to hear a metronome preview of the current tempo and signature.


Signature

The song signature can be set to a value between 2/4 and 7/4. Most songs have a signature of 4/4, meaning that 1 bar has 4 beats (i.e. the length of 4 quarter notes). Hold the Preview button to hear a metronome preview of the current tempo and signature.

Effects Tab

Bus structure

In short, effects with FX enabled act only on tracks that have FX enabled. The other effects are applied on all tracks except the ones with the crossed out FX icon. The following diagram illustrates the audio signal flow:



- Tracks are treated separately depending on the FX bus setting.
- Effects are always applied in the following order: pitch bend, amplifier, delay, equalizer, filter, reverb.
- If the amplifier effect (overdrive) is enabled, it's applied to the tracks like a pre-fader effect in order to have a high overdrive even on quiet tracks.
- All effects with the FX checkbox enabled are applied to the mix of all tracks with FX bus setting.
- This is added together with the rest of the tracks (those without FX bus setting)
- The rest of the effects are applied to the mix (those effects with the <u>FX checkbox</u> disabled)
- The tracks with a no-FX setting are now added to the mix.
- The limiter is applied, according to the master gain.

Common Controls



Power button

Simply switches the effect on or off.

Limit to FX tracks checkbox

Puts the effect into the FX bus, meaning that it will be applied only to those tracks which have FX enabled (blue FX icon in the track list). All the other effects are still applied to all tracks after the FX effects are processed.

Preview button

Identically to the instrument tab's preview button, it plays one or more notes (alternating) with the current instrument.

Default button

Resets the current effect's settings to the preset values.

Volume



Master gain

This is not the device gain, instead it controls the gain of the internal limiter. High values may lead to unwanted volume compression or distortion, low values may not produce the desired volume. Different volumes may be required depending on your output route (the device's internal speaker, or earphones, or loudspeakers).

In technical terms, this setting is required because if all playing instruments are mixed (added up), the resulting values will in most cases be much higher than 65535 (the 16 bit border) and clipping would occur. The limiter uses a smooth mathematical function (a curve) to compress larger numbers into the 16 bit range. The master gain slider controls the slope of this curve.

Device volume


Brings up a popup with a slider which has the same function as the iPhone's hardware volume buttons. If the iPhone's internal speaker is used (not recommended), be sure not to turn it all the way up. If you connected external speakers, set this slider to maximum and control the volume via the speaker's volume controls for the best audio quality.

Decibel meters

These gauges indicate the current output level of each of the stereo channels.

Reverb

Reverb simulates a room of a certain type (Hall/Canyon/Room) and size. If stuttering occurs during playback, decrease the reverb quality.



Reverb size

Controls the size of the sound space. In larger spaces, the reverb is audible for a longer period of time. The size also depends on the selected reverb style, e.g. the largest room reverb is smaller than the largest canyon reverb.

Reverb brightness

Low brightness gives the impression of a darker room (using a low pass filter), while maximum brightness leaves the reverb unfiltered.

Reverb stereo spread

Controls the perception of stereo wideness of the reverb space. In technical terms, this slider sets the delay between the reverb reaching the left and the right channel.

Reverb mix (wet/dry)

The mix slider controls the relation of the dry sound (the original, without the effect applied) and the wet sound (the effect's result).

Reverb style

Selects the type of reverb (room, hall, canyon). Each style uses a different algorithm, thus the size slider has a different effect for each style.

Reverb quality

Reverb requires a lot of processing power. In order to prevent playback stuttering on older devices or with complex songs, decrease the reverb quality. In technical terms, the reverb algorithm stays the same but the number of filters used in the reverbation filter chain is decreased.

Remember settings for each style (iPad only)

As you change the reverb type, the previous settings you made for this type are recalled. If this checkbox is disabled, the reverb sliders remain unchanged if you change the reverb type.

Delay

A delay repeats the original sound in a certain time interval set by the timing buttons/switch and the song tempo. The result is then fed back into the delay, resulting in many repetitions.



Timing buttons

The selected note length will define the time interval of the delay, together with the song tempo.

Timing switch

Dotted timing is 50% longer, triplet timing is 33% shorter.

Feedback

Controls the gain of the feedback. Low values will limit the effect to just one audible repetition, high values will make the total delay duration very long.

Delay mix (wet/dry)

The mix slider controls the relation of the dry sound (the original, without the effect applied) and the wet sound (the effect's result).

Equalizer

The 3-band equalizer has fixed frequencies at 800Hz and 5kHz. Tap or move anywhere in the 3 areas to set the gain of bass, middle and treble tones. The range is -10dB to +10dB, the volume is automatically adapted to avoid clipping.



Amplifier

The amplifier simulates overdrive by clipping the sound. It is a pre-fader effect, thus allowing high overdrive even if a track's volume is quiet.



Overdrive

Controls the amount of distortion, i.e. the input gain for the amplifier.

Style

Changes the mathematical function, resulting in a different timbre.

Filter



The filter effect is a resonant low-, high-, or band-pass filter. The cutoff frequency and the resonance can be set by moving the crosshair, or by tilting the device if the accelerometer is enabled. The <u>filter track</u> in the mixer holds the recorded events (which can be deleted there).

For synth sounds and drum kits, this is a very useful effect. Enable the accelerometer control, switch to the keyboard tab and play or record something while gently tilting the device from one side to the center. A commonly used effect is, with the filter type set to low pass, changing the cutoff frequency from low to high, while keeping the resonance low.

Resonance/Frequency display

The crosshair indicates the current values of the cutoff frequency (x axis) and the resonance (y axis). Move the crosshair to change the values. This can also be performed while recording.

Beware: high resonance values may lead to unpleasantly loud and high tones.

Filter type switch

The filter type defines how the cutoff frequency influences the sound.

- Lowpass: All frequencies above the selected cutoff frequency are dampened (attenuated). The sound remains unchanged if the crosshair is in the lower right corner.
- Highpass: The effect behaves inverse to the lowpass. All frequencies below the selected cutoff frequency are dampened. The sound remains unchanged if the crosshair is in the lower left corner.
- Bandpass: Frequencies above and below the selected cutoff frequency are dampened. The sound remains unchanged if the crosshair is at the bottom center.

Filter accelerometer axis

If the accelerometer is enabled, tilting it in any direction changes the cutoff and the resonance. The sound remains unchanged if the device lies flat on a surface.

• X+Y: Tilting along the x axis changes the cutoff frequency, while the y axis changes the resonance. Starting from the centered position, all 4 quadrants are symmetrical, i.e. tilting the device to the far left has the same effect as the far right.

- X: Filter and cutoff frequency are both changed if the device is tilted in the x axis.
- Y: Filter and cutoff frequency are both changed if the device is tilted in the y axis.

Accelerometer sensitivity

With the sensitivity set to low, the device needs to be tilted almost 90 degrees to achieve the maximum effect. At high sensitivity, small movements are sufficient to set the filter values to maximum.

Snap back checkbox

If snap back is enabled and the crosshair is moved, it snaps back to its original location after you release it.

Pitch



If the pitch bend effect and the <u>accelerometer button</u> in the keyboard tab are enabled, the pitch of the currently played notes can be influenced by tilting the device.

Unlike most MIDI sequencers, Music Studio stores pitch bend data per note, not just per track. This means that two simultaneous notes on the same track can have different pitch bend data (events). The big advantage of this method is that editing a note automatically affects the pitch bend data for this note, but does not affect any other notes on the track (other software sequencers commonly ask if you want to move the pitch bend data too, this is obsolete with this method).

In the piano roll editor, notes with pitch bend data have a different texture (a vertical color gradient).

Semitone slider

Set the pitch bend range with the semitone slider from +/-1 to +/-24 semitones.

Sensitivity slider

The tilt angle required to bend the maximum semitone range is controlled with the sensitivity slider. The text to the right of the sliders clarifies the behavior of the current setting (e.g. the device needs to be tilted 45 degrees to achieve a pitch bend of 8 semitones).

Pitch bend accelerometer axis

This pulldown menu selects if the pitch bend reacts to tilt in the x or the y direction.

Pitch bend invert axis checkbox

Enable it to invert the behavior of the current accelerometer axis, e.g. moving down (instead of up) will increase the pitch.

Pitch bend record mode

The recording mode controls how existing pitch bend data is treated at recording.

- In overwrite mode, existing pitch bend events on the recorded track are overwritten by the new ones.
- Overdub mode preserves existing pitch bend data and stores the new pitch bend events only for newly recorded notes.

Projects Tab

Introduction



In Music Studio, songs create are referred to as projects. The projects tab can be used to create new projects, load, save and delete existing songs, or to export songs into WAV or MIDI files which can be transferred to your Mac/PC.

Projects are stored in the .xms file format, a custom and small format for Music Studio. It contains:

- Tracks, their recorded notes and parameters
- Song tempo, signature, markers
- Effects settings
- Keyboard layout (number of rows, positions, size)
- Metronome settings (volume, type, precount)
- Some user-interface settings (selected track, state of the loop-button etc.)


Setup tab preferences are not contained in an .xms file, i.e. they remain unchanged if a project is loaded.

Filename textfield



If a project is selected, its name is displayed in the textfield. To save the current song, tap the textfield to bring up the keyboard (be patient, this may take a few seconds on older devices) and enter the filename, then tap save. Tap the X icon on the right of the textfield to clear it.

File list



The list displays the type, name and length (or size) of every file. Demo songs and beats are organized in separate folders. Select a file to view its details (date, size) in the area below the list. Double tap a file or a folder to open it. Files with the following extensions are listed:

• xms: Music Studio project

• beat: Music Studio beat

• wav: uncompressed wave file in RIFF format

• mid or midi: MIDI file

Beats

Beats contain one or more loopable drum tracks which can be appended to a song. Tapping a beat immediately plays a preview, which simplifies the process of finding the beat you are looking for. Tap the save button in the beats directory to save the current song's drum tracks as a beat.

If the current song is empty, loading a beat applies its tempo and reverb settings and enables loop playback and recording. Otherwise, a popul lets you choose to append the beat tracks to the current song or to replace all beat (drum) tracks of the current song with the beat's tracks.

In practice, beats are great to start a song with, and are also handy for trying out different rhythms for an existing song. When appending a beat to an existing song, you may want to use the Sequencer's repeat button to manually loop (extend) the beat to the duration of the song.

iTunes File Sharing

Music Studio's file list can be accessed via iTunes to transfer files between your iDevice and your Mac/PC.

- Connect your device with the USB cable and launch iTunes on your Mac/PC.
- In the devices section of the left list, click on your device and select the Apps section in the menu on the top.
- A list of apps which support file sharing is displayed below the "Sync Apps" list.
- Select Music Studio to display its files in the Documents list.
- Drag and drop a file into this list to copy it into Music Studio, or from this list onto your desktop to transfer it onto your Mac/ PC. Keep in mind that Music Studio will only open with with the following extensions: xms, beat, mid, midi.
- Folders cannot be accessed individually, but they can be copied to your desktop as a whole.

Note: iTunes file sharing is available on all iPhone, iPod touch and iPad models with iOS 3.2, iOS 4.0 or higher.


File Sharing

The applications listed below can transfer documents between your iPad and this computer.

Apps



MusicStudio Documents



File Associations

Any .xms or .mid file you find on the web or receive per email can be opened directly with Music Studio. Tap any .xms or MIDI file in an application like Safari or Mail and select "Open with Music Studio" to load this file with Music Studio. Prior to loading, the file is copied into Music Studio's Inbox folder for later use. Saving files manually into the Inbox folder is not possible.

Buttons



New

Creates a new project, deleting all tracks and resetting all effect parameters in the process.



Load

Loads the selected file. You can also double tap a song to load it. If the song requires instruments which are not present in your instrument list (i.e. not yet purchased), they are substituted by the closest matches from the available instruments and a popup informs you about that.



Save

Saves the current song with the filename in the textfield. If the textfield is empty, the keyboard opens and the file is saved when you tap done.



Delete

Deletes the selected file.



Export

The export button does not export the current song, but the selected file. Songs can be exported into MIDI and WAV format. Choose the desired format and tap ok. The selected file will be loaded, exported and your current project will be loaded again.

The format of an exported wav file is 44kHz 16bit stereo. If the "apply markers" checkbox is enabled, only the range between the left and the right song marker of the selected song is exported. For the export process, the polyphony is automatically set to 128.

Exported MIDI files are format 1 files, i.e. each track is written into a MIDI track on a separate MIDI channel. Instruments are translated to closely match the GM (General MIDI) standard voices. Pitch bend is always compressed to the default MIDI range of +/- 2 semitones.

Tip: Before exporting to WAV, save the song with reverb quality set to high.



Server

If your device is in the same WiFi (WLAN) network as your Mac or PC, files can be exchanged by tapping the server button and entering the displayed URL into the Mac or PC's browser.

In order for the Bonjour URL (e.g. http://My-iPhones-Name.local:8080) to work, PCs need to have Bonjour installed (comes with iTunes). Otherwise, use the IP (e.g. http://192.168.1.3:8080) to access the files.

In the browser, right click a file and select Download (or "Save target" or something similar depending on your browser) to save it on your hard disk drive.

Choose a file from your hard drive and click the import button to copy an .xms, .mid, .midi or .zip file onto your iDevice. Zip files are decompressed automatically on upload.

Read this section in the FAQ if you experience problems with the WiFi server.



Setup Tab

Differences on the iPad

On the iPad, all settings are organized on one screen, while on the iPhone/iPod touch they are split up into sub screens.

General settings



Latency

The time interval between your finger touching a key in the keyboard tab and the sound being audible is called latency. Low latency is required for a musician to feel connected with the virtual instrument and to play fast pieces. However, on slower devices, high CPU load can lead to stuttering/crackling in the audio output. This can happen if a complex song with many tracks is played back or if the device is busy with background tasks like mobile phone network processes. To avoid these performance dropouts, the latency can be increased, however the keyboard's responsiveness will suffer.

You might want to choose the lowest possible latency for recording and a higher latency to ensure stutter-free editing and playback.

Polyphony

Polyphony defines the maximum number of notes that can be played simultaneously. High polyphony requires more CPU and can lead to stuttering/crackling in the audio output, but low polyphony can result in notes fading out too soon.

If it is set to 16 and at one point during playback, the song would require 17 notes to be played simultaneously, the oldest note will quickly be faded out to allow the new one to play. The required polyphony of a song depends on the number of simultaneous notes on all tracks, and heavily on the release times. When exporting a song to a wav file, a polyphony of 128 is applied.

In addition to this setting, the polyphony is automatically restricted for each track to 16 (8 on devices prior to the iPhone 4).

Continuous playhead movement

This checkbox appears only on the iPhone 3GS, iPod Touch 2nd generation, iPad and newer devices. In order to save CPU power, this setting is off by default and the playhead in the tracks tab moves only from beat to beat. Enable it to trade a lot of CPU power for more precise playhead movement (may introduce playback stuttering).

Lock interface orientation (iPhone only)

Per default, the interface is adapted to the current device orientation, i.e. if the home button is left or right in landscape orientation. If this checkbox is enabled, the current interface orientation is locked.

On the iPad, use the hardware switch beside the volume buttons to lock the interface orientation.

Hardware section

The hardware setup section indicates if <u>compatible hardware</u> (like the <u>Line 6 MIDI Mobilizer</u>) is connected. In this case, the Configure button becomes active and shows a popup with <u>hardware specific settings</u>.

Restore defaults button

Brings up a popup asking you if the factory defaults should be restored. This means resetting all preferences in the setup tab and creating a new song. Saved songs (i.e. all files in the projects tab file list) will remain unchanged.

Keyboard settings



Velocity control

Enable velocity to control the note volume while playing on the keyboard. If set to Touch-Y, the volume depends on where you touch a key (upper end quiet, lower end forte). The accel setting allows you to control the note volume with the accelerometer by tilting the device in the selected axis.

Snap to white keys

If enabled, scrolling in the keyboard tab will snap to the nearest white key.

Allow touches between black keys

If enabled, white keys can be touched in the area between the black keys. Otherwise, white keys can only be touched on the area below the black keys.

Allow touches on key borders

Allow touches on key borders If disabled, an invisible 5% border is between the white keys in order to minimize accidental touches.

German key labeling

The German key naming system uses the letter H instead of B and B instead of A#. If checked, key labels on the keyboard tab and the piano roll editor's display use this naming convention.

Auto quantization

To save time, quantization can be automatically applied after each recording on the keyboard. The default setting is off, meaning that the sequencer or the piano-roll editor need to be utilized in order to quantize notes. Keep in mind that automatic quantization can lead to undesirable results and is not undoable. It is recommended for bass and drum recording.

Transposition

If you tap a C on the keyboard with the transposition set to +2, a D will be played. The transposition range of -11 to +11 semitones allows you to play in a different key without having to learn the melody again.

Accelerometer settings

Pitch bend, the filter effect and the keyboard note velocity can be controlled via the accelerometer. The global settings in this screen might come in handy if you use the accelerometer a lot. The crosshair in the accelerometer panel indicates the current device tilt as perceived by the app (after processing the calibration, threshold and reactivity settings).



Threshold slider

Device tilt is ignored up to the angle set the threshold slider. At a high threshold, the device can be tilted by about 15° until accelerometer vales are recorded.


Reactivity slider

High reactivity increases the effect of accelerometer noise while low reactivity leads to sluggish behavior (which may be a desired effect in some cases).

Calibration

Tap the calibrate button to set the current device tilt as the centered position. The Reset Calibration button restores it.

Interface settings



Instruments tab

Keep attack/release times on instrument change (iPhone only)

If this is disabled, each time you select an instrument its default attack and release time will be set. If enabled, the current track's attack/release durations are kept when you select another instrument.

On the iPad, this setting is included right in the instruments tab.

Tracks tab

Scroll on the margins when moving notes

If enabled, the sequencer and the piano roll editor automatically scroll if you move a selection to the edge.

Centered zooming

If checked, the pinch gesture in the tracks tab zooms into the center of the song ruler. Otherwise, the left song ruler position stays fixed and the right border changes when zooming.

Effects tab

Remember reverb settings for each type (iPhone only)

As you change the reverb type, the previous settings you made for this type are recalled. If this checkbox is disabled, the reverb sliders remain unchanged if you change the reverb type.

On the iPad, this setting is included right on the reverb screen in the effects tab.

Metronome settings



Volume

The volume slider controls the gain of the metronome tick sound.

Style

Choose between five metronome sounds. The higher pitched (first) sound indicates the beginning of a bar, the other sound marks the other beats.

Precount

Set how many bars a recording will be precount. This is handy if you want to record the first note at the very beginning of the song (beat 1.1). Without precount, there wouldn't be enough time to tap the record button and immediately play the first note. Additionally, precount helps to get in line with the rhythm before you start playing (recording).

For example if precount is set to 2 bars, the playhead position is at the beginning of the song (1.1) and you tap the record button, the playhead will count 2 bars from -2.1, -1.1 until the recording starts at 1.1.

Precount only at song start

If checked, precount is only applied if the left song marker is positioned at the beginning of the song. If it is not checked and the left song marker is for example at position 7.1, a 1-bar precount will begin at 6.1.

External Hardware

The external hardware section in the setup indicates if compatible hardware (like the <u>Line 6 MIDI Mobilizer</u> or the <u>Akai SynthStation 25</u>) is connected. In this case, the *Configure* button becomes active and shows a popup with hardware specific settings. If an external keyboard is detected, the <u>latency</u> is automatically set to *ultra low*.

Hardware Configuration Popup



The MIDI hardware configuration popul looks different depending on the kind of hardware connected. For the Akai SynthStation 25, it shows the battery level. For the Line 6 MIDI Mobilizer and CoreMIDI devices, it presents parameters for input and output. Port selection is available for CoreMIDI devices only.

MIDLIN

Connect the MIDI IN port to any keyboard's MIDI OUT port. Every key that you press on the hardware keyboard will be received by the app. The channel can be set to the following values:

- TRACKS: Incoming MIDI events are routed to the corresponding tracks 1-16 (if existing).
- ALL: All incoming MIDI events are routed to the keyboard (upper row), regardless of their channel.
- 1-16: Only events with this channel are routed to the keyboard.

In addition to note on/off events, it responds to the following MIDI events:

- Note velocity
- Sustain pedal (also called hold switch) on/off
- Pitch wheel: the pitch bend effect will be enabled automatically
- Mod wheel: if the filter effect is enabled, it can be controlled with a hardware mod wheel (MIDI CC01)
- Volume and pan: the selected track's parameters can be set with a hardware controller (MIDI CC07 and CC10)

MIDI OUT

Connect the MIDI OUT port to any keyboard's MIDI IN port to control it with your iDevice. Note on, note off and pitch bend MIDI events are sent to the connected device as you play on the keyboard tab, tilt the iDevice or play back a song. The channel can be set to the following values:

- TRACKS: MIDI events from all tracks are sent to the MIDI OUT port during playback. A track's channel is defined by its track number. Tracks above number 16 are mapped to channel 1.
- 1-16: Only the keys touched in the keyboard tab are transmitted to the selected MIDI channel. When a song is played back, recorded notes will not be transmitted in this mode.

Port

If a CoreMIDI device is connected, the input and output ports can be selected. The possible values are ALL (send to or receive from all ports) and the respective port number. For example, most MIDI-USB adapter cable have two plugs and thus two ports.

MIDI Panic

Tap the MIDI Panic button to silence both Music Studio and the device connected through MIDI Mobilizer. This can be useful in the rare event that notes are "hanging".

Send Params

The Send Params button transmits the current song's instruments, track volumes and track pan parameters. If a multitrack MIDI device is connected, it can be set to mimic Music Studio's current track setup with this button.

Line 6 MIDI Mobilizer

The MIDI Mobilizer adds MIDI in/out ports to the iPhone, iPad or iPod Touch.

Akai SynthStation 25

Your iPhone or iPod Touch can be inserted into the SynthStation to input notes with its 2-octave velocity sensitive keyboard. The audio output is routed through the SynthStation where you can connect headphones or use RCA jacks. Here is how Music Studio responds to the SynthStation's controls:

- Pitch bend wheel: controls the pitch bend
- Mod wheel: controls the filter effect
- Drums button:
 - When pressed while piano keys are pressed, this button acts as a sustain button.
 - Otherwise (when no piano keys are down) it selects a drum kit.
- Synth buttons: select various synth instruments
- Program prev/next: change the current track's instrument to the previous/next one in the instrument list
- Octave down/up: change the keyboard's position on Music Studio's full 7 octave keyboard. Note: the on-screen keyboard is independent of these buttons.

Core MIDI

For devices with iOS 4.2 (or later), connected Core MIDI devices are supported. Certain USB keyboards and USB-MIDI adapter cables can be connected to the iPad via the *Camera Connection Kit*, if they match the CoreMIDI standard and have very low USB power requirements or an external power supply.

Troubleshooting Guide

For more support-related discussions, please refer to the Forum on the product website.

Rebooting properly

Rebooting your device will resolve most issues. Press and hold the Home and the Sleep/Wake button for about 10 seconds until the Apple logo appears (don't slide to power off, hold longer).

Key presses have a very high latency / I cannot press more than 2 keys at once

- Deactivate the Zoom feature in the Accessibility section of the iPhone's Settings. Launch the Settings app, tap General, Accessibility, Zoom and turn it off.
- Switch to a lower latency in the general section of the setup tab.
- If you still experience latency problems, please properly reboot your device.

The audio output stutters

Decrease the reverb quality, increase the <u>latency</u>, or decrease the <u>polyphony</u> to reduce the CPU load. If the song (together with the effects, latency and polyphony settings) requires more CPU speed than your device can provide, audio stuttering occurs.

The audio output sounds noisy

Use earphones or external speakers because the device's internal speaker cannot cope with the broad frequency spectrum of the instruments. Additionally, decrease the master gain (in the volume section of the effects tab) to prevent clipping. This might be necessary if many instruments play simultaneously, because their gains add up.

My purchased instruments do not appear on my second device

Simply enter the shop, tap the restore button in the upper right corner, enter your iTunes username and password, and wait for the instruments (which you already purchased) to appear in the instrument list. This process can take up to a few minutes depending on your connection speed (preferably WiFi).

Some notes end too early during playback

Increase the polyphony in the setup tab, but keep in mind that this may lead to stuttering with complex songs on older devices.

The server does not work

Tunes file sharing is the recommended method of transferring files. However, if you must use the WiFi Server, follow these steps: Make sure that your device is connected to the same WiFi network as your Mac/PC. If your browser does not load the Music Studio webpage, enter the IP address (numbers) instead of the Bonjour address (device name) in the browser's address bar, followed by a colon and the number 8080. If the problem persists, try a different browser, try disabling your PC's firewall or try bypassing your router by setting up an ad-hoc network on your Mac/PC. Step by step instructions:

- Connect to a WiFi network with your iPhone
- Connect to the same WiFi network with your Mac/PC
- Tap the Server button in Music Studio
- Enter the IP address (without www) followed by the port in your Mac/PC's browser, e.g. 192.168.1.3:8080
- Right click a file and select Download (or "Save target" or something similar depending on your browser) to save it on your hard drive.

Version history

Version 1.6.1

Released in February 2011

Major new features

- Clipboard: tap and hold a selection in the SEQ screen to copy and paste between songs
- Auto-quantization after recording (in the keyboard setup)
- Tempo precision increased to 0.1 bpm
- Compatibility with the new MIDI Mobilizer firmware

Minor changes

- MIDI port selection added to the Core MIDI configuration popup
- Fix: MIDI out channels were ignored over Core MIDI
- Fix: MIDI stop signal was not sent over Core MIDI
- Fix: Invalid pitch bend values were sent through MIDI out
- Fix: the pitch bend range slider influenced recorded note's pitch bend values (now it acts on live notes only)
- Fix: Recording with an external keyboard did not work if the MIDI IN channel was set to "Tracks"
- iPad: behavior of "Sync keyboard row instruments" improved
- Tapping on the tracks tab a second time switches to the MIX screen
- The file list ignores the case of the file extension, it shows .MID files as well as .Mid
- The file list updates immediately after a sync with iTunes file sharing
- MIDI file import: restrictions on signature message length loosened (for compatibility with Sony Acid Pro)
- Stability and performance improvements

Version 1.6

Released on December 18, 2010

Major new features

- Akai SynthStation 25 support
- · Core MIDI support
- Rearrange tracks in the MIX screen (tap and hold the icon)
- Keyboard transposition setting

Minor changes

- · Beats improved
- MIDI IN channel selection
- When recording with a MIDI keyboard, the sustain pedal increases the note lengths
- Track editing operations don't pause playback anymore
- Note selection is retained when switching from the piano-roll editor to the SEQ screen
- Fix: Moving the playhead during a track editing operation cancelled the editing mode
- Fix: Instruments were not loaded if the track was changed with the Line 6 MIDI Mobilizer connected

• Stability and performance improvements

Version 1.5.1

Released on November 1, 2010

Bug fixes regarding

- Line 6 MIDI Mobilizer support
- Audio output and bluetooth accessories
- Pitch-bend recording
- Crashes at launch
- Opening xms and midi files from Safari or Mail

Minor changes

- Additional polyphony choices (8 and 12) for older devices
- iPad: if "Sync keyboard rows" is on and a track is selected, the lower row's instrument is changed too
- MIDI Mobilizer configuration popup improved
- Fix: latency was not automatically set to "Ultra low" if the MIDI Mobilizer was already connected at launch
- Fix: opening midi files with pitch-bend events resulted in exceptionally large xms files
- Fix: wav export was stuck if a note ended after the song end point
- Fix: when an instrument was changed during playback, the selected instrument was silenced
- Fix: graphics glitch when changing (loading) an instrument on newer devices
- Fix: the projects tab's Load button did not display its down state correctly
- Fix: the Redo button did not work in some cases

Version 1.5

Released October 13, 2010

Major new features

- New free instruments: HipHop Kit, Sound Effects Kit, Harp, Harmonica, 9 Synths
- New instruments in the shop: Sitar, Shakuhachi, 8-bit kit
- 100 beat loops
- iTunes file sharing (iOS 3.2, iOS 4 and later)
- File associations (open .xms and .mid files from Safari and Mail)
- iPhone 4 retina display supported
- Line 6 MIDI Mobilizer supported
- Improved multitouch on the keyboard (slide and play simultaneously)
- Battery consumption improved
- Lots of performance optimizations and stability improvements

Major bug fixes

- iPad-only fix: audio route changes (connecting earphones) disrupted audio output
- iPad-only fix: changing the metronome type did not load the new metronome until the next launch
- Fix: accelerometer pitch bend with adaptive calibration was too sensitive
- Fix: some MIDI files could not be loaded
- Fix: signature 7/4 was not selectable in the tempo popup on the iPhone

- Fix: when deleting congruent notes, both were deleted instead of only one
- Fix: volume and pan changes did not affect notes that were already playing

Keyboard tab

- Even when keys are touched, the slide/pinch gestures on the menu can now be performed (scroll the keyboard with one finger on the menu while holding down some keys with your other hand).
- Menu buttons can be tapped while keys are touched (e.g. to tap stop while you are still holding down some keys)
- iPad: number of keyboard rows and keyboard row syncing setting are now retained

Tracks tab

- Piano-roll editor: note colors improved, now ranging from blue to green to yellow, overlapping notes are red
- Piano-roll editor: selection of overlapping and congruent (red) notes improved
- Fix: filter recording cleared the filter track (was overwrite instead of overdub)
- Fix: filter track visualization improved
- Fix: zooming in the piano-roll editor sometimes was erratic
- Fix: too many undo points were created when drawing notes

Projects tab

- Folders for demos and beats
- Save the drum tracks of the current song as a beat in the beat folder
- Fix: wav export now strictly applies the markers if enabled

Setup tab

• External hardware section for Line 6 MIDI Mobilizer

Version 1.4

Released August 3, 2010

Major new features

- iPad optimization: Music Studio is now a universal binary
- New free instrument: a gorgeous grand piano
- iOS 4 multitasking enabled

Keyboard tab

- Tap and hold the metronome button to bring up the tempo popup
- Fix: accelerometer pitch bend did not conform to the desired pitch range in some cases

Instruments tab

• iPad: checkbox to synchronize the keyboard rows

Projects tab

- Fix: File with the .midi extension were not recognized (only .mid was)
- Fix: signatures 2/4 and 7/4 were not loaded correctly
- New demo added: "Club on fire" by TecWeed

Misc

- A tempo or signature change is now an undo step
- Fix: undo unloaded used samples in rare cases
- Fix: orientation changes were not handled correctly by the loading screen
- Various memory optimizations and stability improvements

Version 1.3

Released June 29, 2010

Major new features

- Pitch bend effect (accelerometer controlled)
- Filter effect (with accelerometer control)
- Improved help (internet connection no longer required)
- Reduced instrument shop prices
- New shop layout
- Note editing in the tracks tab is now possible during playback
- File loading times greatly reduced

Major bug fixes

- Fix: crash on iPad if more than 5 fingers touched the screen
- Fix: audio route changes (connecting earphones) resulted in distorted audio
- Fix: MIDI import prioritized channels instead of tracks

Keyboard tab

- Accelerometer button (to enable accelerometer effects)
- Interface orientation is locked while keys are touched
- Fullscreen button moved to layout mode
- · Gestures tutorial is displayed at the first launch
- Fix: key label mode was not remembered

Tracks tab

- New tempo and signature popup
- Tempo +/- buttons auto-in/decrease on hold
- Additional signatures available (2/4, 7/4)
- New metronome style
- New special track to display recorded filter effect data (visible if the filter effect is on)
- Fix: undo reset recent track and keyboard row changes
- Fix: rare crash at manual playhead scrolling

Effects tab

• Filter and pitch bend effect

Projects tab

- MIDI import/export includes pitch bend events
- File format improved

Setup tab

- New layout
- Accelerometer and metronome settings
- New setting: continuous playhead movement
- New setting: reverb configuration is remembered per type
- New setting: track editing tips

Version 1.2.1

Released May 6, 2010

Major bug fixes

- Fix: Critical crash which occurred if a song with reverb set to room and low quality was loaded
- Fix: Rare crash in the keyboard tab

Version 1.2

Released April 28, 2010

Major new features

- New high-quality reverb algorithms with stereo spread
- 3 reverb qualities (higher quality requires more CPU and can lead to stuttering on older devices)
- Key velocity (volume) can be controlled via touch on the keyboard or the accelerometer (enable this in the setup tab)
- Piano-roll: 'selection change mode' toggles the selected range (instead of just single notes)

Major bug fixes

- Fix: crash if a low memory warning occurred twice
- Fix: crash on iPad at launch
- Lots of stability and performance improvements

Keyboard tab

• When recording, playback continues if a tab or the record button is tapped.

Instruments tab

- Fix: lower row instrument selection
- Fix: lower row instrument was not fully loaded in low-memory situations
- Fix: instrument previews did not play all notes as intended
- Fix: instrument demo songs were copied at every app launch

Tracks tab

- MIX: double tap a track's icon and slide your finger to select a color
- SEQ: song is cleared if the last (one and only) bar is cut
- Piano-roll: when exiting the draw mode, the done button draws the note if ok was not tapped
- Piano-roll: vertical lock button added to move mode
- Piano-roll: 1/64th note button added
- Piano-roll: quantization button added to length mode
- Fix: move and draw did not reload samples in low-memory situations
- Fix: when drawing notes, the position was shifted after tapping ok
- Fix: autoscrolling when moving notes in piano-roll view

Effects tab

- Equalizer performance improved (requires less CPU)
- Fix: volume gauges were not reset to zero

Projects tab

• File list performance greatly improved

- The last session's song name is displayed at the bottom
- Export wave popup: checkbox added to apply the song markers
- Fix: loading a song did not switch the tracks tab to the mix screen
- Fix: crashed if files with special chars in the filename were uploaded via the server

Undo

- Fix: undo/redo remembers selected track and loop/metronome settings
- Fix: undo/redo popup displayed '? notes' after loop recording

Version 1.1

Released April 7, 2010

Major new features

- 4 new free instruments: trombone, rock bass, synth brass, marimba
- In-app shop with 48 studio-quality instruments
- 24 hour trial period to test all instruments
- Instruments arranged in 4 groups: classic, band, electronic, world
- Texture memory usage reduced by 50%, offering much more memory for loading instruments
- Huge performance and stability improvements
- Pause button in the tracks tab
- Playhead mode (tap the LCD) for quick playhead positioning in the keyboard and tracks tabs
- Horizontal lock button added to the piano-roll editor move menu
- Undo improved: redo added, popup (press the button for 2 sec.), undo files are kept throughout switching tabs
- Loading screen displays tips (touchable)

Audio

- Existing instruments improved: clarinet, flute, grand piano
- Sustain looping improved
- Pan now preserves the volume
- New demo songs

Keyboard tab

- · Loop recording fixed
- Fixed some small touch input issues

Instruments tab

- Instrument list scrollbar is touchable
- Tonal range warning popup substituted by touchable warning triangles in the tracks tab

Tracks tab

- MIX: double tapping the pan knob sets it to 0
- SEQ: view can now fully zoom out
- SEQ: transpose is no longer restricted to the playable range
- Fix: piano-roll view was restricted to the playable range, notes outside were not editable
- Track list icons rearranged in MIX and are now identical in SEQ mode
- Piano-roll: maximum zoom factor increased
- Piano-roll: note coloring changed, from dark blue (silent) to cyan (loudest)
- Piano-roll: vertical zoom is now unrestricted (zoom out to all keys is possible)

- Piano-roll: vertical zoom buttons added (tap the magnifier button)
- Piano-roll: instrument icon moved to the bottom right corner
- Fix: piano-roll preview did not consider the note's velocity
- Fix: piano-roll move only worked if all selected notes were on-screen
- Fix: touches are now ignored during lengthy editing operations

Projects tab

- When loading a song with unpurchased instruments, they are substituted and a popup lists the required instruments
- Song loading time decreased (especially if it shares instruments with the previous song)
- File list drawing speed improved
- Fix: protection against file corruption (e.g. in case of incoming call)
- Fix: exported wav file ended too soon in rare occasions if the delay effect was on

Setup tab

- Added: Keep attack/release at instrument change
- Removed: LCD playhead scrolling (is now obsolete with the new playhead mode)
- Removed: Remember last state at exit

Version 1.0.3

Released December 12, 2009

Major new features

- Browser interface (WiFi server) now offers search, selection and delete functionality
- Piano-roll editor offers snap-to-grid when moving notes
- Zoom buttons and minimap added to the tracks tab (access via the magnifying glass button)
- Volume bars for L/R beside each track's instrument icon

Major bug fixes

- Fix: exported wave files had the wrong tempo
- Fix: note selection did not work with signature 6/4
- Improvements and bug fixes
- Audio engine optimizations (decreased CPU load)
- Amplifier is now a pre-fader effect (this enables heavy distortion even for low-gain tracks)

Keyboard tab

- Separate zoom factors for each keyboard row
- Fix: precount did not work at loop recording
- Fix: "Loading samples" popup was not shown when entering the keyboard tab
- Fix: stuttering when playing on 2 rows is fixed (as a trade-off the instrument icon always shows the upper row's instrument)

Instruments tab

• Attack and release times are set to default when selecting an instrument

Tracks tab

- Appearance of muted tracks improved
- Piano-roll: maximum zoom factor increased
- Fix: draw mode auto-scrolling in the piano-roll editor
- Fix: selection in the piano-roll editor was cleared at vertical scrolling

- Fix: entering the piano-roll editor in an empty track showed the highest octave
- Fix: SEQ selection was moved down if the empty area below the tracks was touched
- Fix: SEQ delete did not clear the selection
- Fix: some instruments were not audible at playhead scrubbing

Projects tab

- Special characters are automatically removed from filenames
- File list automatically scrolls to the recently saved file
- Fix: export button could be tapped even it was disabled
- Fix: files with long filenames (abbreviated in the list) were not loaded
- Fix: remaining disk space calculation sometimes returned wrong results
- Fix: rare crash when loading a file
- Fix: rare crash when creating a new project
- Fix: dates of decompressed zip file contents were wrong

Misc.

- Shadow added to the fonts in the popup window
- Loading screen adapts to the device orientation
- Animation of popup dialogs is skipped if playback is running
- Fix: font was blurry in the help tab
- Fix: "Loading textures" popup was shown only partially
- Fix: restore defaults while playback caused a crash
- Fix: the previous instrument was still selected under the loading instrument popup

Version 1.0.2

Released November 4, 2009

Major new features

- MIDI import
- ZIP files can be uploaded via WiFi (and are automatically decompressed)
- Increased and configurable polyphony (up to 64)
- Decreased latency
- Tracks are scanned for errors and repaired when loading an xms or midi file
- Double tap on a track in the MIX to switch to the piano roll editor at this position Projects tab: File list scroll bar is touchable for quick scrolling

Keyboard tab

- Fix: pressed keys were released at song stop or loop end
- Fix: loop recording fixed
- Fix: undo button is active as soon as a note was recorded

Tracks tab

- Tempo can be adjusted without pausing playback
- Tracks tab performance greatly increased
- Tracks tab scrolling speed increased, zoom speed adapts to the current zoom factor
- Double tapping on the tempo (above the track list) switches to the tempo screen
- Fix: space between bar number labels on the ruler is now adapted to their width
- Fix: stuck notes if solo was disabled but other tracks were still solo

- Fix: SEQ repeat now updates the right song marker
- Fix: SEQ zoomed to song end when tapping the SEQ button
- Fix: SEQ selection was cleared if only one bar was tapped
- Fix: crash if more than 32767 notes were drawn
- Fix: strange behavior of undo after duplication fixed
- Fix: quantize popup text was mispositioned

Projects tab

- Fix: crashes could occur if more than 256 files were in the list
- Fix: long file names are trimmed in the file list
- Fix: file extensions were case sensitive
- Fix: an autosave is now generated immediately after a new project is created
- Fix: file list scrolled to top after deleting a file
- Fix: files are now sorted case insensitive
- Fix: when loading a future file format, a warning popup is displayed
- Fix: possible crash after a song was saved under heavy CPU load

MIDI and WAV export

- Wave export switches polyphony to 128
- Fix: exported MIDI files had the sequence name TempoTrack instead of the song's name
- Fix: MIDI export track properties were wrong in some cases (pan, volume, attack, release)
- Fix: exported wave file memory estimation was off
- Fix: wave export cut the song before all effects were faded out in rare cases
- Fix: calculation of available space at wave export gave wrong results
- Fix: timeouts while exporting wave files in rare cases

Misc

- Stability improvements
- Audio engine performance improvements
- Pulldown menus added for latency and polyphony settings
- New and improved demo songs
- Fix: popups with a loading bar were not rendered correctly
- Fix: possible crash at undo
- Fix: rare crash at instrument change while playback
- Fix: rare crash at the loading screen
- Fix: device orientation change sometimes did not rotate the screen
- Fix: effects screen required too much rendering performance

Version 1.0.1

Released October 3, 2009

Major new features

- MIDI export
- Resolution increased to 1/192 note (48 ticks per beat)
- Overlapping notes are colored orange
- New and improved demo songs

Major bug fixes

- Dotted and triplet quantization produced wrong results
- Texture manager improved (effects textures were not loaded in low memory situations)
- Server had to be enabled multiple times until it worked in an ad-hoc network
- Wave export added too much silence after the song end

Keyboard

- Fix: Undo did not work properly after loop recording
- Fix: Some key's up/down state was wrong after track switching or song stop
- Fix: When recording in loop mode, keys pressed during the loop end are now cut
- Fix: When recording is stopped, pressed keys are now recorded as note-off events

Tracks tab

- Notes covering other notes are colored orange, congruent notes are selected separately
- MIX: double tapping a track brings up the piano roll editor
- SEQ: accidental song length increases while moving are prevented
- SEQ: the edit button can now be tapped even if only empty bars are selected from one track
- Playhead cursor line precision improved
- Fix: Sequencer repeat left empty bars in place
- Fix: Ruler sometimes did not draw the first or the last bar line
- Fix: SEQ ruler scrolling was possible on the track icons
- Fix: SEQ move gestures worked on tracks only
- Fix: Piano roll editor auto zoom improved
- Fix: SEQ was not updated if touched outside a track in new selection mode
- Fix: Undo in piano roll editor draw mode improved
- SEQ: In bar edit mode, it is now easier to select the last bar in order to add new bars at the song end
- Maximum zoom factor, scrolling and sliding speed increased

Effects tab

- Equalizer and amp are now updated in real-time (while you are moving the controls)
- Fix: Volume needles were not updated at song stop
- Fix: Crackling noise occurred when reverb/delay/equalizer were changed

Projects tab

- Status info improved (last action with time stamp)
- Fix: Tapping the projects tab textfield clear button crashed the app
- Fix: New/load project confirmation popup sometimes was not shown even if the project was changed
- Fix: Export button was tap-able even if no song was selected
- Fix: Wave export sometimes showed the not-enough-memory popup without reason
- Fix: Audio engine was not restarted after export
- Fix: Entering Japanese or special characters in the project name could lead to a crash
- Fix: File list scrolling was possible everywhere
- Fix: Undos were not purged at load or new project
- Export popup displays the filename

Misc

- Preview buttons now always plays the first preview type (one note) first
- Fix: Settings were lost if the app was quit while it was still loading
- Fix: Crackling noise and crash in rare circumstances

Version 1.0

Initial version. Released September 4, 2009